

MAST Primer for JWST

Key elements of MAST interfaces are summarized here, and include Portal tutorials for users new to MAST.

On this page...

- [Getting Started with MAST](#)
 - [Login](#)
 - [Exclusive Access Data](#)
 - [MAST Interfaces](#)
 - [Web Applications](#)
 - [API](#)
- [Portal Tutorials](#)
 - [Searches with the Portal](#)
 - [Target Name or Coordinates](#)
 - [Program ID](#)
 - [JWST Instrument Keywords](#)
- [Data Retrieval Options](#)
 - [Direct Download](#)
 - [Download Basket](#)
 - [Streaming Download](#)
 - [Download via cURL Script](#)
 - [Batch Download](#)
- [API Tutorial](#)
- [What's in the Box](#)
 - [File Names and Content](#)
- [For Further Reading...](#)
 - [Reference Documents](#)
 - [User Support](#)

Getting Started with MAST

Login

Certain operations require that you log into MAST. This includes access to most data from active JWST observing programs. See [MAST Accounts](#) for details.



If you have a MyST account and login to MAST you may [subscribe to notifications](#) about JWST program data availability, even for observations that have not yet executed.

Exclusive Access Data

All data from JWST will eventually become public, and anyone may conduct searches for JWST data. However, when data fall under an **exclusive access period (EAP)** the files may only be retrieved by authorized persons. To retrieve EAP data from MAST:

- You **must** have a MyST account. See this URL to create one: <https://proper.stsci.edu/proper/authentication/auth>
- Login to MAST at any point prior to retrieving data. See [MAST Accounts](#) for details.
- Those with MyST accounts must be authorized by the PI of the program to retrieve EAP data.
 - PIs of observing programs may grant access to Co-Is (or anyone with a MyST account) by visiting [MyST](#) and selecting [Registered UsersUpdateManage Access to Exclusive Access Science Data](#).

MAST Interfaces

Web Applications

MAST offers a multiple web-based tools to search for and retrieve science and engineering data, or for other information. Links to these tools appear in the table below.

Search Type	Select a collection...	URL
Observations of a target or field	MAST Observations by Object Name or RA/Dec	https://mast.stsci.edu/portal/Mashup/Clients/Mast/Portal.html
Observations Matching a Program ID	Observations by Program ID	

Files matching Instrument Keyword Values	<i>JWST Instrument Keywords</i>	
Wavefront Sensing products	<i>JWST WSS</i>	
DOI Portal		https://mast.stsci.edu/portal/Mashup/Clients/DOI/DOIPortal.html
Calibrated Engineering Data		https://mast.stsci.edu/portal/Mashup/Clients/jwstedb/jwstedb.html
Keyword Dictionary		https://mast.stsci.edu/portal/Mashup/Clients/jwkeywords/index.html



Browser Issues

Note that the MAST Portal has incompatibilities with certain browsers and settings. In particular, pop-up blockers must grant an exception for the mast.stsci.edu domain. For details see [Introduction to the MAST Portal](#) in the [Portal Guide](#).

API

Many users find scripted access to MAST searches and data retrievals to suit their needs better. The most popular interface offered is the Python package [astroquery.mast](#). A brief tutorial is appears near the end of this article, and more extensive documentation is offered in the [JWST Archive Manual](#) in the [Using MAST APIs](#) chapter.

Portal Tutorials

The MAST Portal search panel is shown below. It is a starting point for your interactions with MAST.

All of the searches described below start with selecting the appropriate *collection* for a search, from the drop-down menu shown at right.

Search results are displayed below the search panel, as shown in the example below.

Home Page

MAST: m57 r=1m

Displaying 169 of 663 Total Rows

MESSIER 057, radius: 0.01667°

Footprints: All

Filters

Keyword/Text Filter

Filter All Columns

Mission

Name

Quantity

JWST

(169 of 279)

SPITZER_SHA

(0 of 110)

HST

(0 of 100)

HLA

(0 of 96)

ILUE

(0 of 33)

Show 5 More

Instrument

Calibration Level

Name

Quantity

3

(49 of 299)

2

(48 of 179)

-1

(72 of 178)

4

(0 of 7)

Proposal ID

List View

Album View

Edit Columns...

Table Display: All

Show Preview: Show Cutout:

	Actions	Instrument	Filters	Observation ID
3		NIRSPEC	F100LP	jw01539-c1016_s00004_nirspec_f1
4		NIRSPEC	F100LP	jw01539-o003_s00004_nirspec_f10
5		MIRI	F1000W	jw01558-o001_t001_miri_f1000w
6		MIRI	F1130W	jw01558-o001_t001_miri_f1130w
7		MIRI	F1280W	jw01558-o001_t001_miri_f1280w
8		MIRI	F1500W	jw01558-o001_t001_miri_f1500w
9		MIRI	F1800W	jw01558-o001_t001_miri_f1800w
10		MIRI	F2100W	jw01558-o001_t001_miri_f2100w
11		MIRI	F2550W	jw01558-o001_t001_miri_f2550w
12		MIRI	F560W	jw01558-o001_t001_miri_f560w
13		MIRI	F770W	jw01558-o001_t001_miri_f770w
14		MIRI/IMAGE	F560W,	jw01558001001_xx101_00001_miri
15		MIRI/IMAGE	F560W,	jw01558001001_xx102_00002_miri

AstroView

18:53:30.790 +33:02:27.77

18:53:35.014 +33:01:42.89

RA DEC

hh:mm:ss/deg

Results consist of Filter dialogs (*left*); a table of matched results (*center*) showing rows for public (*white background*), Exclusive Access (*yellow background*, with the padlock icon), and planned but not yet executed observations (*orange background*); and the AstroView tool (*right*) which shows the spatial extent (*colored footprints*) of the exposures superimposed on an image of the sky. For details see [Field Guide to the Portal](#).

Searches with the Portal

Many types of Portal search return **Observations**, which are really collections of all available data products, including uncalibrated, intermediate, fully calibrated, and combined science data. See [Linkages in the Portal](#) to learn more about how various kinds of data products are associated in the Portal. See [Download Basket](#) to learn how to select and download one or more of these types of products.

Target Name or Coordinates



A basic search will return Observations from all hosted MAST missions. **This search will provide access to all levels of JWST data products.**

	Instruction	Notes
1	Select 'MAST Observations by Object Name or RA/Dec' from the 'Select a collection...' pull-down menu at the left of the search panel.	
2	Enter a target name and (optionally) a search radius, which will be resolved to coordinates. See Basic Search for syntax rules. m57 r=1m	<div>and enter target:</div> <div>m57 r=1m</div> <div> Show Examples... Random Search Advanced Search </div>
3	Click the Search button to the right of the target dialog.	<div>Search </div>

4	<p>Optional: Filter the results in the left panel by selecting Mission: <i>JWST</i> and the Instrument(s)/configuration(s). For example: <i>MIRI/IFU</i> and <i>NIRSPEC/IFU</i></p>	 <p>The screenshot shows a 'Filters' panel with two sections: 'Mission' and 'Instrument'. In the 'Mission' section, 'JWST' is selected with a quantity of 124 of 143. Other missions listed include SPITZER_SHA (0 of 128), HST (0 of 120), HLA (0 of 96), and IUE (0 of 33). In the 'Instrument' section, 'MIRI/IFU' is selected with a quantity of 20 of 20. Other instruments listed include FUV (0 of 1), GPC1 (0 of 5), IRAC (0 of 12), IRS (0 of 116), LWP (0 of 7), LWR (0 of 7), MIRI/IMAGE (0 of 15), NIRCAM/IMAGE (0 of 4), and NIRSPEC/IFU (104 of 104).</p>
5	Evaluate the search results grid. It will look something like the example .	

An advanced search allows you to customize the query by additional attributes, and can return Observations for all hosted MAST missions. This search will provide access for access to all levels of JWST data products (unless you choose to restrict the calibration level).

	Instruction	Notes
1	Select <i>MAST Observations by Object Name or RA/Dec</i> from the 'Select a collection...' pull-down menu on the upper-left.	
2	To search using more criteria than target name or position, click the Advanced Search link below the target dialog.	<p>and enter target:</p> <p>Enter object name or RA and Dec to cone search</p> <p>Show Examples... Random Search Advanced Search</p>


3	<p>Search by multiple criteria with filter dialogs. In this case:</p> <ul style="list-style-type: none"> Mission: <i>JWST</i> will greatly accelerate the query Instrument: <i>MIRI*</i> (i.e., all configurations of MIRI). Note typing the name of the instrument in the dialog box will accelerate the selection. Target Name: <i>NGC6720*</i>. Including the asterisk (wildcard) at the end will select the target name and variants, which may include offset positions. 	
4	Click the search button at upper-left.	
5	The search results grid will look similar to the example . Select one or more Observations by ticking the box(es) at the left of the results table, then choose a download method .	


Program ID

This type of search will return all Observations for a given observing program (a.k.a. proposal number). This is a quick way for Investigator Teams to search for all data related to their science program.



This search will match program IDs for both JWST and HST, even though the results for one mission are not scientifically related to the other. It is easy to filter the results table for the mission of interest.

	Instruction	Notes
1	Select <i>MAST Observations by Proposal ID</i> from the 'Select a collection...' pull-down menu on the upper-left.	
2	Enter one or more proposal numbers, separated by commas, then click the Search button.	

3	Filter the results to select the common target vv191. (Note the variations in the spelling.)	
4	The search results grid will look something like the example . Select one or more Observations by ticking the box(es) at the left of the results table, then choose a download method .	

JWST Instrument Keywords

This type of search for JWST data provides a much larger set of criteria, including important metadata that are not available in standard searches such as:



- the flag for time-series observations (`tsovisit`)
- exposure type (`exp_type`, which could indicate, e.g., coronagraphic observations)
- observation sequence identifier (`observtn`)
- program category (`category`, e.g., COM and ERS where all data are instantly public)

Beware that this type of search matches data for only one selected JWST instrument, and only the *highest-level calibrated science FITS files*.



Highest-level products only!




This kind of search will **not** provide access to ancillary files, nor to uncalibrated (e.g., Level-1b) files if higher-level products exist. It will also not match calibrated files that are not in FITS format, such as source catalogs or light curves.

	Instruction	Notes
1	Select <i>JWST Instrument Keywords</i> from the 'Select a collection...' pull-down menu on the upper-left, and select the instrument of interest from the pull-down menu below that.	
2	Click the Advanced Search button.	



MRP files only

This option **does not** download all available products, but rather the most highly calibrated and combined science products. It is similar to downloading from the basket when the [Minimum Recommended Products](#) option is selected.



	Instruction	Notes
1	Click the file icon in one of the rows in the results table.	
2	After a moment a pop-up dialog may appear, asking if the file should be saved. Note that the files are zipped for transfer efficiency. <div> Whether a dialog appears, and the specific wording in the dialog, depend upon browser settings. The location where the files will be written also depends upon your browser settings.</div>	











Download Basket


This form of download is intended for retrieving multiple observations at once, and for retrieving all (or only selected) types of products. There are three options: immediate streaming download (which imposes a size limit), and retrieval by curl script or ftp staging (which do not).

Streaming Download

This example applies to results that contain Observations, rather than individual files (as you would have after an Instrument Keyword search).




	Instruction	Notes
1	Select one or more rows in the results grid.	
2	Click the basket button just above the grid to add the selected files to your download basket.	
3	The Download Manager window may look something like that below. Note that the number of files associated with JWST Observations can be nearly 7500 in this case).	
4	The next task is to select which files to include in the download bundle, which consists of two steps:	


4a	<p>Recommended: use one or more filter dialogs to select types of products to include or exclude.</p> <ul style="list-style-type: none"> Note that selecting Minimum Recommended Products will hide lower-level (uncalibrated) products from the file selector tree. Selecting SCIENCE and INFO categories will include all files necessary for re-running the calibration pipeline on your own machine. Not including the AUXILIARY category will have the effect of excluding guide-star files. This may greatly decrease the volume of data (7282 files in this example) Selecting the UNCAL group will include uncalibrated (Level 1-b) files. <div style="border: 1px solid green; padding: 5px; margin-top: 10px;">  Your selection for the MRP checkbox will be remembered for subsequent downloads during your Portal session. </div>	<div>  Recommended Products <div> <input checked="" type="checkbox"/> Minimum Recommended Products (2 of 2) </div> </div> <div>  Product Category <div> <input type="checkbox"/> AUXILIARY (0 of 7282) <input checked="" type="checkbox"/> SCIENCE (33 of 98) <input type="checkbox"/> PREVIEW (0 of 82) <input checked="" type="checkbox"/> INFO (34 of 34) </div> </div> <div>  Group <div> <input checked="" type="checkbox"/> I2D (17 of 17) <input checked="" type="checkbox"/> POOL (17 of 17) <input checked="" type="checkbox"/> ASN (17 of 17) <input checked="" type="checkbox"/> UNCAL (16 of 16) <input type="checkbox"/> DATEINTS (0 of 16) </div> </div>
4b	<p>Required: Select specific files or sub-directories of files to include.</p> <ul style="list-style-type: none"> check the boxes of observations and/or files you wish to download. Note: checking the box of a parent observation automatically checks the boxes of all child files in the dataset. optional: click the triangle on the left to review the detailed contents of the sub-directory. 	<div> Displaying 132 of 7496 Total Files </div> <div> Files <div> Mission > Observation > File <div>   JWST <div>  <input checked="" type="checkbox"/>  jw01558-o001_t001_miri_f1000w <div> <input checked="" type="checkbox"/> jw01558-o001_20220820t20531 <input checked="" type="checkbox"/> jw01558_20220820t205310_pox <input checked="" type="checkbox"/> jw01558-o001_t001_miri_f1000 <input checked="" type="checkbox"/> jw01558-o001_t001_miri_f1000 </div> </div> </div>   jw01558001001_02105_00001_mir <div> <input type="checkbox"/> jw01558-o001_20220820t20531 </div> </div> </div>

8	<p>Select the format for the download package from the pull-down, then click the Download button</p> <p>Optional: Check the "Remove completed files from basket" box. This will purge download basket, which may help avoid confusion the next time you prepare to download files using the basket.</p>	
---	---	---

Download via cURL Script

This type of retrieval is asynchronous and has no limits to the volume of data to download. It is more robust against internet interruptions, and can be resumed if interrupted.

	Instruction	Notes
1	Follow instructions 1–7 for Streaming Download (above).	
2	Select <u>Curl</u> from the file Format pull-down menu.	
3	<p>Save the cURL shell script in a directory where you wish the data files to be stored.</p> <div data-bbox="219 1402 714 1554">  Whether a dialog appears, and the specific wording in the dialog, depend upon browser settings. The location where the files will be written also depends upon your browser settings. </div>	

4	<p>Bring up a shell and execute the downloaded script.</p> <p>Note: If you are retrieving Exclusive Access Protected data, you will need to either provide your MyST login credentials, or have set an environment variable with your Auth.MAST token, in order for the shell to complete the retrieval successfully.</p> <div>  The cURL script is targeted to a bash shell. Specifying bash on the command line allows it to be invoked from any unix shell. </div>	<pre>bash MAST_2018-10-31T2028.sh</pre>
---	---	---






MAST Auth Tokens

Authentication for access to EAP data via a cURL or other scripts is managed in MAST via tokens. See [MAST API Tokens](#) to learn how to create or update a MAST.auth token.

Batch Download



Staging files for **ftps** retrieval is currently supported for a few MAST missions (including JWST and HST), but not all. It is highly recommended to instead retrieve large numbers of files via cURL scripts.

	Instruction	Notes
1	Follow instructions 1–6 for Immediate Download (above).	
2	Click the Batch Retrieval button.	
3	<p>Select <i>staging</i> from the file Delivery Method pull-down menu and (if you are not logged in) provide the email address where you wish the notification to be sent.</p> <p>Note: If you are logged in to MAST, the e-mail address on record will be pre-filled.</p>	
4	Acknowledge the email pop-up notification, and check your email at the delivery address you specified.	
5	The email notification will give the location of the files that have been staged.	
6	Use a third-party client such as Cyberduck or wget to retrieve the files.	

API Tutorial

The following tutorial introduces the basics of MAST queries with the [astroquery.mast](#) package. More extensive documentation is offered in the [JWST Archive Manual](#) in the [Using MAST APIs](#) chapter.

The set of all available parameters for this type of query is summarized [here](#). Consider a search for JWST/NIRCam observations in observing program 1073, using the F277W filter. Use the `.query_criteria()` method.

```
matched_obs = Observations.query_criteria(
    obs_collection = 'JWST'
    , proposal_id = '1073'
    , instrument_name = 'Nircam'
    , filters = 'F277W'
)
```

The result is an **astropy** Table object, with one row per matched observation.



If for a particular query you are not interested in observations from any mission except JWST, specify it with the parameter `obs_collection='JWST'`. This will narrow the list of possible matches considerably, and speed up your query.

Having found Observations that match your criteria, the next step is to fetch a table of data products associated with each Observation.



Some observations contain huge numbers of associated or linked files, sometimes in excess of 10,000 products. This is particularly true for NIRSpec MSA, or MIRI and NIRCам slitless spectroscopy, but may also be true for large mosaics of images. Each observation is likely to contain many files in common, such as guide-star files and ancillary products.

It is strongly recommended to retrieve product lists one or a few at a time from each observation to avoid server timeouts, and then to construct a set of unique products from the combined observations to avoid large numbers of duplicated products.

The following retrieves a list of tables of data products for each observation, and returns combined table containing unique data products.

```
if (matched_obs > 0):
    t = [Observations.get_product_list(obs) for obs in matched_obs]
    files = unique(vstack(t), keys='productFilename')
```

If at least one observation matched the search criteria the above call returns a table of unique products, one per row, which could number in the hundreds or thousands. You may wish to filter the results by masking all but a limited number of file suffixes and excluding certain sub-strings.

The selected products may now be downloaded to your local machine. Note that you will need to login with a valid [Auth.MAST](#) token to download exclusive access (EAP) data. If the token is needed but not supplied, the you will be prompted to enter one.

You may download all the products in the files table, or select a subset if you prefer. The following will select L-1b products (i.e. the raw, uncalibrated, *_uncal.fits) from the data product list for retrieval. Other types of products may instead be selected, either by matching product name sub-strings or selecting named products in the `productSubGroupDescription`.

```
manifest = Observations.download_products(
    files,
    productSubGroupDescription='UNCAL',
    curl_flag=True
)
```

Setting the optional `curl_flag` parameter to **True** will instead download a **bash** script that contains **cURL** commands to fetch the files at a later time. This approach is highly recommended for large numbers of files. The name of the download script will be something like: `mastDownload_YYYYMMDDhhmmss.sh`, where the latter part of the name is a numeric timestamp. What remains is to invoke the downloaded script on your machine to retrieve the files.

What's in the Box

All data products for all selected observations will be bundled together for delivery. When the Zip or tar file is unpacked, data for each observation/visit/exposure will appear in a separate sub-directory.

For each sub-directory, the data bundle includes by default the highest-level data products, *plus all parent data*. For example, if an observation/visit/exposure combination resulted in Level-2 data products, all Level-1 products would automatically be included unless the user explicitly chooses otherwise.



The Download Manifest

The zip (or tar) file will include a file called **MANIFEST.HTML** which lists each file name, a short description, and whether access is restricted. It will also note any files that could not be downloaded and the reason why (e.g., if you do not have permission to retrieve them).

File Names and Content

The semantic content of science files may be inferred from the file suffix, and the filename signature. For example, files ending in `_uncal.fits` are Level-1b uncalibrated science products. See the JWST [Data Product Types](#) documentation for details.

For Further Reading...

Reference Documents

- MAST [Portal Guide](#)
- [JWST Archive Manual](#)
- [JWST User Documentation Home](#) (JDox)
- [JWST Pipeline Documentatino](#) (ReadTheDocs)
- [astroquery.mast](#) documentation

User Support

- **Archive Help Desk:** archive@stsci.edu
- JWST [Help Desk](#)